

proportional to the applied voltage; $I \propto \Delta V$. If the proportionality holds, we can write $\Delta V = IR$, where the proportionality constant R is called the **resistance** of the conductor. In fact, we define the **resistance** as the ratio of the voltage across the conductor to the current it carries:

$$R \equiv \frac{\Delta V}{I} \quad [17.3]$$

Resistance →




FIGURE 17.7 A uniform conductor of length l and cross-sectional area A . The current I in the conductor is proportional to the applied voltage $\Delta V = V_b - V_a$. The electric field \vec{E} set up in the conductor is also proportional to the current.



GEORG SIMON OHM
(1787–1854)

A high school teacher in Cologne and later a professor at Munich, Ohm formulated the concept of resistance and discovered the proportionalities expressed in Equation 17.5.



An assortment of resistors used for a variety of applications in electronic circuits.

Resistance has SI units of volts per ampere, called **ohms** (Ω). If a potential difference of 1 V across a conductor produces a current of 1 A, the resistance of the conductor is 1 Ω . For example, if an electrical appliance connected to a 120-V source carries a current of 6 A, its resistance is 20 Ω .

The concepts of electric current, voltage, and resistance can be compared to the flow of water in a river. As water flows downhill in a river of constant width and depth, the flow rate (water current) depends on the steepness of descent of the river and the effects of rocks, the riverbank, and other obstructions. The voltage difference is analogous to the steepness, and the resistance to the obstructions. Based on this analogy, it seems reasonable that increasing the voltage applied to a circuit should increase the current in the circuit, just as increasing the steepness of descent increases the water current. Also, increasing the obstructions in the river's path will reduce the water current, just as increasing the resistance in a circuit will lower the electric current. Resistance in a circuit arises due to collisions between the electrons carrying the current with fixed atoms inside the conductor. These collisions inhibit the movement of charges in much the same way as would a force of friction. For many materials, including most metals, experiments show that **the resistance remains constant over a wide range of applied voltages or currents**. This statement is known as **Ohm's law**, after Georg Simon Ohm (1789–1854), who was the first to conduct a systematic study of electrical resistance.

Ohm's law is given by

$$\Delta V = IR \quad [17.4]$$

where R is understood to be independent of ΔV , the potential drop across the resistor, and I , the current in the resistor. We will continue to use this traditional form of Ohm's law when discussing electrical circuits. A **resistor** is a conductor that provides a specified resistance in an electric circuit. The symbol for a resistor in circuit diagrams is a zigzag line: .

Ohm's law is an empirical relationship valid only for certain materials. Materials that obey Ohm's law, and hence have a constant resistance over a wide range of voltages, are said to be **ohmic**. Materials having resistance that changes with voltage or current are **nonohmic**. Ohmic materials have a linear current–voltage relationship over a large range of applied voltages (Fig. 17.8a). Nonohmic materials have a nonlinear current–voltage relationship (Fig. 17.8b). One common semiconducting device that is nonohmic is the **diode**, a circuit element that acts like a one-way valve for current. Its resistance is small for currents in one direction (positive ΔV) and large for currents in the reverse direction (negative ΔV). Most modern electronic devices, such as transistors, have nonlinear current–voltage relationships; their operation depends on the particular ways in which they violate Ohm's law.

QUICK QUIZ 17.4 In Figure 17.8b does the resistance of the diode (a) increase or (b) decrease as the positive voltage ΔV increases?

QUICK QUIZ 17.5 All electric devices are required to have identifying plates that specify their electrical characteristics. The plate on a certain steam iron states that the iron carries a current of 6.00 A when con-

nected to a source of 1.20×10^2 V. What is the resistance of the steam iron?
(a) 0.050 Ω (b) 20.0 Ω (c) 36.0 Ω

Resistivity

Electrons don't move in straight-line paths through a conductor. Instead, they undergo repeated collisions with the metal atoms. Consider a conductor with a voltage applied across its ends. An electron gains speed as the electric force associated with the internal electric field accelerates it, giving it a velocity in the direction opposite that of the electric field. A collision with an atom randomizes the electron's velocity, reducing it in the direction opposite the field. The process then repeats itself. Together, these collisions affect the electron somewhat as a force of internal friction would. This step is the origin of a material's resistance.

The resistance of an ohmic conductor increases with length, which makes sense because the electrons going through it must undergo more collisions in a longer conductor. A smaller cross-sectional area also increases the resistance of a conductor, just as a smaller pipe slows the fluid moving through it. The resistance, then, is proportional to the conductor's length l and inversely proportional to its cross-sectional area A ,

$$R = \rho \frac{l}{A} \quad [17.5]$$

where the constant of proportionality, ρ , is called the **resistivity** of the material. Every material has a characteristic resistivity that depends on its electronic structure and on temperature. Good electric conductors have very low resistivities, and good insulators have very high resistivities. Table 17.1 lists the resistivities of various materials at 20°C. Because resistance values are in ohms, resistivity values must be in ohm-meters ($\Omega \cdot \text{m}$).

TABLE 17.1

Resistivities and Temperature Coefficients of Resistivity for Various Materials (at 20°C)

Material	Resistivity ($\Omega \cdot \text{m}$)	Temperature Coefficient of Resistivity [$(^\circ\text{C})^{-1}$]
Silver	1.59×10^{-8}	3.8×10^{-3}
Copper	1.7×10^{-8}	3.9×10^{-3}
Gold	2.44×10^{-8}	3.4×10^{-3}
Aluminum	2.82×10^{-8}	3.9×10^{-3}
Tungsten	5.6×10^{-8}	4.5×10^{-3}
Iron	10.0×10^{-8}	5.0×10^{-3}
Platinum	11×10^{-8}	3.92×10^{-3}
Lead	22×10^{-8}	3.9×10^{-3}
Nichrome ^a	150×10^{-8}	0.4×10^{-3}
Carbon	3.5×10^5	-0.5×10^{-3}
Germanium	0.46	-48×10^{-3}
Silicon	640	-75×10^{-3}
Glass	10^{10} – 10^{14}	
Hard rubber	$\approx 10^{13}$	
Sulfur	10^{15}	
Quartz (fused)	75×10^{16}	

^aA nickel-chromium alloy commonly used in heating elements.





FIGURE 17.8 (a) The current–voltage curve for an ohmic material. The curve is linear, and the slope gives the resistance of the conductor. (b) A nonlinear current–voltage curve for a semiconducting diode. This device doesn't obey Ohm's law.

Handwritten calculations:

$$A = \pi r^2 = \pi (0.002)^2 = 1.26 \times 10^{-5} \text{ m}^2$$

$$V = 120 \text{ V}$$

$$I = 6.00 \text{ A}$$

$$R = \frac{V}{I} = \frac{120 \text{ V}}{6.00 \text{ A}} = 20 \Omega$$

$$\rho = \frac{RA}{l} = \frac{(20 \Omega)(1.26 \times 10^{-5} \text{ m}^2)}{2.0 \text{ m}} = 1.26 \times 10^{-4} \Omega \cdot \text{m}$$